



Subject	How to Install Java
Version	1.0
Issue date	02/04/2013
Beneficiaries	All ASYCUDA World Users
File	How_to_Install_Java.doc
Status	Final
Checked by	ASYCUDA division, National Board of Revenue
Copyrights	United Nations Conference on Trade And Development

How to read this document



This symbol indicates advice and recommendations. Information on best practices and recommended procedures related to the current topic is contained here.



Keyword Definition



This symbol indicates a warning. Information on common pitfalls or dangers associated with the current topic is contained here.



This symbol indicates an example to further illustrate the current topic.

*Source 1 -
This is an example
of source code*

Source code.



Figure1 - This is an example of figure

This document demonstrate how to install Java Runtime Environment (JRE) on Windows to be used with ASYCUDA World system.

1. Downloads

To have maximum compatibility with ASYCUDA system, it is recommended to install JRE version 1.6_17. You can download the file from following link. Alternatively, the file is available to download in customs website.


<http://www.oracle.com/technetwork/java/javasebusiness/downloads/java-archive-downloads-javase6-419409.html#jre-6u17-oth-JPR>

Accept licence agreement, choose the relevant file to download based on the specification of your PC:


1. For Windows OS (32-bit) download: [jre-6u17-windows-i586.exe](#)
2. For Windows OS (64-bit) download: [jre-6u17-windows-x64.exe](#)
3. For Linux OS (32-bit) download: [jre-6u17-linux-i586.bin](#)
4. For Linux OS (64-bit) download: [jre-6u17-linux-x64.bin](#)

2. Installation

Run the installer file, downloaded in step above. If you see security warning, image below, click on run.




Once installation started, click on the **Install** button to accept the license agreement, which will then proceed with the installation.



During installation, you'll see a series of different applications that take advantage of the Java Runtime Environment (JRE)




The installation may take a few minutes to completely load on your system. Once the installation has been completed, you will be prompted with the below message. Please click on **Close** button to exit the installer.



Disabling Java Automatic update

By default, Java updates itself automatically when a newer version is available. In order to prevent automatic update, you will need to configure the Java Plug-in. Go to your Windows **Start** button, then to **Settings** and then select **Control Panel**.



Once in control panel, locate “Java” icon and double click to open it.



In the new Java Control Panel window click on the **Advanced** tab, and then expand the **JRE Auto-Download** heading. Ensure that **Never Auto-Download** is selected and then click **OK** to close the window.

